



## CISCO Software Manager Server User Guide

[Home](#) » [Cisco](#) » CISCO Software Manager Server User Guide 



### Installing CSM Server

This chapter provides information about the installation and uninstallation procedure of CSM server. This chapter also describes how to open the CSM server page.

#### Contents

- [1 Installation Procedure](#)
- [2 Opening the CSM Server Page](#)
- [3 Uninstalling the CSM Server](#)
- [4 Documents / Resources](#)
  - [4.1 References](#)

## Installation Procedure

To download the latest information about the currently posted software packages and SMUs, the CSM server requires an HTTPS connection to the Cisco site. The CSM server also checks periodically for a newer version of the CSM itself.

To install the CSM server, run the following command to download and execute the installation script: `$ bash -c "$(curl -sL https://devhub.cisco.com/artifactory/software-manager-install-group/install.sh)"`



### Note

Instead of downloading and executing the script, you can also choose to download the following script without executing it. After downloading the script, you can manually run it with some additional options if necessary:

```
$ curl -Ls https://devhub.cisco.com/artifactory/software-manager-install-group/install.sh
```

```
-O
```

```
$ chmod +x install.sh
```

```
$ ./install.sh --help
```

CSM Server installation script:

```
$ ./install.sh [OPTIONS] Options:
```

```
-h
```

Print help

```
-d, --data <dir>
```

Select the directory for data share

```
--no-prompt
```

Non interactive mode

```
--dry-run
```

Dry run. Commands are not executed.

```
--https-proxy URL
```

Use the HTTPS Proxy URL

```
--uninstall
```

Uninstall CSM Server (Remove all data)



### Note

If you do not run the script as a “sudo/root” user, you are prompted to enter the “sudo/root” password.

## Opening the CSM Server Page

Use the following steps to open the CSM server page:

### SUMMARY STEPS

1. Open CSM server Page by using this URL: `http://<server_ip>:5000` at a web browser, where “server\_ip” is the IP address or Hostname of the Linux server. The CSM server uses TCP port 5000 to provide access to the Graphical User Interface (GUI) of the CSM server.
2. Login to the CSM server with the following default credentials.

### DETAILED STEPS

	Command or Action	Purpose
Step 1	Open CSM server Page by using this URL: <code>http://&lt;server_ip&gt;:5000</code> at a web browser, where “server_ip” is the IP address or Hostname of the Linux server. The CSM server uses TCP port 5000 to provide access to the `Graphical User Interface (GUI) of the CSM server.	<b>Note</b> It takes approximately 10 minutes to install and launch the CSM server page.
Step 2	Login to the CSM server with the following default credentials.	<ul style="list-style-type: none"> <li>• Username: root</li> <li>• Password: root</li> </ul>
		<b>Note</b> Cisco strongly recommends you to change the default password after the initial login.

### What to do next

For more information about using the CSM server, click Help from the top menu bar of the CSM server GUI, and selecting “Admin Tools”.

## Uninstalling the CSM Server

To uninstall the CSM server from the host system, run the following script in the host system. This script is the same install script that you downloaded earlier with: `curl -Ls https://devhub.cisco.com/artifactory/software-manager-install-group/install.sh -O` to install the CSM server.

```
$ ./install.sh --uninstall
20-02-25 15:36:32 NOTICE CSM Supervisor Startup Script: /usr/sbin/csm-supervisor
20-02-25 15:36:32 NOTICE CSM AppArmor Startup Script: /usr/sbin/csm-apparmor
20-02-25 15:36:32 NOTICE CSM Config file: /etc/csm.json
20-02-25 15:36:32 NOTICE CSM Data Folder: /usr/share/csm
20-02-25 15:36:32 NOTICE CSM Supervisor Service: /etc/systemd/system/csm-supervisor.service
20-02-25 15:36:32 NOTICE CSM AppArmor Service: /etc/systemd/system/csm-apparmor.service
20-02-25 15:36:32 WARNING This command will DELETE all the CSM containers and shared data
folder from the host
Are you sure you wish to continue [yes|No]: yes
20-02-25 15:36:34 INFO CSM uninstalling started
20-02-25 15:36:34 INFO Removing Supervisor Startup Script
20-02-25 15:36:34 INFO Removing AppArmor Startup Script
20-02-25 15:36:34 INFO Stopping csm-supervisor.service
20-02-25 15:36:35 INFO Disabling csm-supervisor.service
20-02-25 15:36:35 INFO Removing csm-supervisor.service
20-02-25 15:36:35 INFO Stopping csm-apparmor.service
20-02-25 15:36:35 INFO Removing csm-apparmor.service
20-02-25 15:36:35 INFO Removing CSM Docker containers
20-02-25 15:36:37 INFO Removing CSM Docker images
20-02-25 15:36:37 INFO Removing CSM Docker bridge network
20-02-25 15:36:37 INFO Removing CSM config file: /etc/csm.json
20-02-25 15:36:37 WARNING Removing CSM Data Folder (database, logs, certificates, plugins,
local repository): '/usr/share/csm'
Are you sure you wish to continue [yes|No]: yes
20-02-25 15:36:42 INFO CSM Data Folder deleted: /usr/share/csm
20-02-25 15:36:42 INFO CSM Server uninstalled successfully
During uninstallation, you can save the CSM data folder by answering “No” at the last question. By answering
“No”, you can uninstall the CSM application and then reinstall it with the preserved data.
```

## Documents / Resources

	<p><a href="#">CISCO Software Manager Server</a> [pdf] User Guide Software Manager Server, Manager Server, Server</p>
---	---

## References

- [User Manual](#)