


DELL Command, Configure Installation Guide

Contents

- [1 DELL Command, Configure Installation Guide](#)
- [2 Introduction to Dell Command | Configure 4.10.1](#)
- [3 Installing Dell Command | Configure 4.10.1 for systems running on Windows](#)
- [4 Uninstalling Dell Command | Configure 4.10.1 for systems running on Windows](#)
- [5 Upgrading Dell Command | Configure 4.10.1 for systems running on Windows](#)
- [6 Dell Command | Configure 4.10.1 for Windows Preinstallation Environment](#)
- [7 Documents / Resources](#)
 - [7.1 References](#)

DELL Command, Configure Installation Guide



Notes, cautions, and warnings

 **NOTE:** A NOTE indicates important information that helps you make better use of your product.

 **CAUTION:** A CAUTION indicates either potential damage to hardware or loss of data and tells you how to avoid the problem.

 **WARNING:** A WARNING indicates a potential for property damage, personal injury, or death.

Introduction to Dell Command | Configure 4.10.1

Dell Command | Configure is a software package that provides BIOS configuration capability for Dell client systems. IT can use this tool to configure BIOS settings and create BIOS packages using the Dell Command | Configure User Interface (UI) or Command Line Interface (CLI).

Dell Command | Configure 4.10.1 supports the following Windows operating systems: Windows 11, Windows 10, Windows Preinstallation Environment (Windows PE).

This guide provides the installation instructions for Dell Command | Configure.

i NOTE: This software was rebranded as Dell Command | Configure after Dell Client Configuration Toolkit version 2.2.1.

- Dell Command | Configure 4.10.1 or later generates a 64-bit SCE with constraints.
- On a 64-bit client machine with a WoW64 subsystem, both 32-bit and 64-bit SCE are generated.
- If a WoW64 subsystem is not present in the client system, and then only a 64-bit SCE is generated.

Topics:

- Accessing Dell Command | Configure installer
- Installation prerequisites
- Supported Platforms
- Supported operating systems for Windows

Accessing Dell Command | Configure installer

The Dell Command | Configure installation file is available as a Dell Update Package (DUP) at dell.com/support. Follow these steps to download DUP:

1. Go to dell.com/support.
2. Under **Which product can we help you with**, enter the **Service Tag** of your supported Dell device and click **Submit**, or click **Detect personal computer**.
3. On the Product Support page for your Dell device, click **Drivers & Downloads**.
4. Click **Manually find a specific driver** for you [model].
5. Check **System Management** checkbox under **Category** dropdown.
6. Locate **Dell Command | Configure** in list and select **Download** on the right side of the page
7. Locate the downloaded file on your computer (in Google Chrome, the file appears at the bottom of the Chrome window), and run the executable file.
8. Follow the on-screen instructions

Installation prerequisites

Installation prerequisites for Windows

- The Dell Command | Configure installation file, Dell-Command-Configure__WIN_4.10.1 _A00.EXE available at dell.com/support.
- Workstation running a supported Windows operating system.
- Administrator privileges on the system to install Dell Command | Configure .
- Microsoft .NET 4.0 to install and run the user interface.
- Microsoft Visual C++ Redistributable for Visual Studio 2019.

i NOTE: Select **Microsoft .NET Framework 4.0** or later on the **Turn Windows features on or off** screen on systems running Windows 7 or later operating systems.

i NOTE: Limited functionality is available if the system does not have a WMI-ACPI compliant BIOS. Update the

BIOS with a compatible version, if available. For more information, see Windows SMM Security Mitigations Table (WSMT) Compliance section in Dell Command | Configure User's Guide.

NOTE: For systems running Windows 7 Service Pack 1, KB3033929 (SHA-2 code signing support for windows 7) and KB2533623 (Insecure library loading fix) must be installed prior to installing Dell Command | Configure.

Supported Platforms

- OptiPlex
- Latitude
- XPS Notepad
- Dell Precision

NOTE: Dell Command | Configure 4.0.0 or later requires platforms supporting WMI-ACPI BIOS. The complete functionalities of Dell Command | Configure is available for the supported platforms, see the Supported platforms list for more information.

NOTE: For the limited functionalities on non-WMI-ACPI compliant platforms, see Windows SMM Security Mitigations Table (WSMT) Compliance section in Dell Command | Configure Version 4.10.1 User's Guide.

Supported operating systems for Windows

Dell Command | Configure supports the following operating systems:

- Windows 11 21H2—22000
- Windows 10 19H1—18362
- Windows 10 19H2—18363
- Windows 10 20H1—19041
- Windows 10 20H2—19042
- Windows 10 21H2
- Windows 10 22H2
- Windows 10 Redstone 1—14393
- Windows 10 Redstone 2—15063
- Windows 10 Redstone 3—16299
- Windows 10 Redstone 4—17134
- Windows 10 Redstone 5—17763
- Windows 10 Core (32-bit and 64-bit)
- Windows 10 Pro (64-bit)
- Windows 10 Enterprise (32-bit and 64-bit)
- Windows 10 Preinstallation Environment (32-bit and 64-bit) (Windows PE 10.0)
- Windows 11 Preinstallation Environment (32-bit and 64-bit) (Windows PE 11.0)

Installing Dell Command | Configure 4.10.1 for systems running on Windows

You can install Dell Command | Configure from the downloaded Dell Update Package (DUP) using the user interface, or perform a silent and unattended installation. You can perform both types of installation using the DUP or a .MSI file.

NOTE: Microsoft .NET 4.0 or later must be installed on the client system for Dell Command | Configure user interface installation.

NOTE: If User Account Control (UAC) is enabled on Windows 10 system, you cannot install Dell Command | Configure in silent mode. Make sure that you have administrative privileges before installing Dell Command | Configure in silent mode.

Related Links:

- [Installing Dell Command | Configure using DUP](#)
- [Installing Dell Command | Configure silently using DUP](#)
- [Installing Dell Command | Configure using the msi file](#)
- [Installing Dell Command | Configure in silent mode using the msi file](#)

Installing Dell Command | Configure using a DUP

Perform the following steps to install Dell Command | Configure using Dell Update Package (DUP):

1. Double-click the downloaded DUP, click **Yes**, and then click **INSTALL**. The Dell Command | Configure installation wizard is displayed.
2. Run the installation wizard.
For more information, see [Running the installation wizard](#).

Installing Dell Command | Configure using the msi file

Perform the following steps to install Dell Command | Configure using the MSI file:

1. Double-click the downloaded Dell Update Package (DUP), and click **Yes**.
2. Click **EXTRACT**.
The **Browse For Folder** window is displayed.
3. Specify a folder location on the system, or create a folder in which you want to extract the files, and then click **OK**.
4. To view the extracted files, click **View Folder**.

The folder contains the following files:

- 1028.mst
- 1031.mst
- 1034.mst
- 1036.mst
- 1040.mst
- 1041.mst
- 1043.mst
- 2052.mst
- 3076.mst
- Command_Configure.msi
- mup.xml

- package.xml

5. To access the Dell Command | Configure installation wizard, double-click **Command_Configure.msi**

6. Run the installation wizard.

For more information, see Running the installation wizard.

After you install Dell Command | Configure , you can use the GUI or the CLI to configure the client systems. For more information about configuring the systems, see the following documents at dell.com/support:

- Dell Command | Configure Command Line Interface Reference Guide
- Dell Command | Configure User's Guide

Running the installation wizard

1. Browse to the folder in which you have extracted the Command_Configure.msi or DUP file.

2. Right-click the MSI or DUP and click **Run as administrator**.

The installation wizard is displayed.

3. Click **Next**.

The **License Agreement** screen is displayed.

4. Read the license agreement and click I accept the terms in the licence agreement, and then click **Next**.

The **Customer Information** screen is displayed.

5. Type the user name and organization, select one of the following options, and then click **Next**.

- For multiple users select **Anyone who uses this computer (all users)**.
- For a single user select **Only for me (Dell Computer Corporation)**.

The custom setup screen is displayed.

6. Click **Next** to install Dell Command | Configure CLI and GUI in the default directory. The default Dell Command | Configure installation directories are:

- For 32-bit system, C:\Program Files\Dell\Command Configure
- For 64-bit system, C:\Program Files (x86)\Dell\Command Configure

The **Ready to Install the Program** screen is displayed.

7. Click **Yes**.

The Installing Dell Command | Configure screen is displayed. When the installation completes, the installation wizard completed screen is displayed.

8. Click **Finish**.


If the Dell Command | Configure GUI is successfully installed, the shortcut for the GUI is displayed on the desktop.

Installing Dell Command | Configure in silent mode using DUP

Perform the following steps to install Dell Command | Configure in silent mode:

1. Browse to the folder where you have downloaded the Dell Update Package (DUP) and then open the command prompt.

2. Run the following command: Dell-Command-Configure__WIN_4.10.1._A00.EXE/s.

 **NOTE:** For more information about using commands, type the following command: Dell-Command-

Configure__WIN_4.10.1._A00.EXE/s or Dell CommandConfigure__WIN_4.10.1._A00.EXE/?.

Installing Dell Command | Configure in silent mode using the msi file

1. Go to the folder where the Dell Command | Configure installer is extracted from the Dell Update Package (DUP).

2. Run the following command: `msiexec.exe /i Command_Configure.msi /qn`

The Dell Command | Configure components are silently installed in the following locations:


- For 32-bit systems, C:\Program Files\Dell\Command Configure.
- For 64-bit systems, C:\Program Files (x86)\Dell\Command Configure.

Installing with supported languages

To perform silent and unattended installation with supported languages, run the following command: `msiexec /i Command_Configure_.msi TRANSFORMS=1036.mst`

To specify the installation language, use the command line option, `TRANSFORMS= .mst`, where is one of the following:

- 1028 — Chinese Taiwan
- 1031 — German
- 1033 — English
- 1034 — Spanish
- 1036 — French
- 1040 — Italian
- 1041 — Japanese
- 1043 — Dutch
- 2052 — Simplified Chinese
- 3076 — Chinese Hongkong

 **NOTE:** If the above mentioned languages or the default operating system languages are not supported, then it displays the English language by default.

Uninstalling Dell Command | Configure 4.10.1 for systems running on Windows


Perform the following steps to uninstall Dell Command | Configure on systems running on Windows:

1. Go to **Start > Settings > Apps > Apps and Features**
2. Select **Add/Remove Programs**.

Upgrading Dell Command | Configure 4.10.1 for systems running on Windows

You can upgrade Dell Command | Configure using a Dell Update Package (DUP) or the MSI file.

NOTE: Microsoft .NET Framework 4 or later must be installed on the client system to ensure a successful Dell Command | Configure user interface installation.

 **NOTE:** If Windows User Account Control (UAC) is enabled on Windows 7, Windows 8, Windows 8.1, and Windows 10 systems, you cannot install Dell Command | Configure in silent mode. Make sure that you have an

administrative privilege before installing Dell Command | Configure in silent mode.

NOTE: This system does not have a WMI-ACPI compliant BIOS, so the limited functionality is available. Update the BIOS with a compatible version, if available. For more information, see Dell Command | Configure Release Notes.

NOTE: You cannot install and upgrade Dell Command | Configure on non-WMI-ACPI in silent mode

Related links:

- Upgrading Dell Command | Configure for systems running on Windows using DUP
- Upgrading Dell Command | Configure for systems running on Windows using the MSI file

Topics:

- Upgrading Dell Command | Configure for systems running on Windows using a DUP
- Upgrading Dell Command | Configure for systems running on Windows using the msi file

Upgrading Dell Command | Configure for systems running on Windows using a DUP

Perform the following steps to upgrade Dell Command | Configure (formerly Dell Client Configuration Toolkit) to the next version:

1. . Double-click the downloaded DUP, and then click **INSTALL**.

The Dell Command | Configure installation wizard is launched.

2. Run the installation wizard, and follow the instructions that are displayed on the screen

Upgrading Dell Command | Configure for systems running on Windows using the msi file

For minor upgrades such as upgrading Dell Command | Configure (formerly Dell Client Configuration Toolkit), perform the following steps:

1. Download the latest installation file, Dell-Command-Configure__WIN_4.10.1._A00.EXE from **dell.com/support**.

2. Extract the installation:

- From the folder where you extracted the file, double-click the Command_Configure.msi file, or
- From the command prompt, browse to the directory where you extracted the file, and then run the following command:

```
msiexec.exe /i Command_Configure.msi REINSTALL=ALL REINSTALLMODE=VOMUS
```

NOTE:The installation wizard screen is displayed followed by “**An older version of Dell Command | Configure is detected on this system. If you continue, installer will remove the older version and proceed to install the latest version. If you cancel the installation of the latest version, the system will not be restored to the previous version of Dell Command | Configure. Do you want to continue?**” message.

3. Follow the instructions on the screen to upgrade.

NOTE: For a silent upgrade, run the following command: msiexec /i Command_Configure.msi REINSTALL=ALL REINSTALLMODE=vmous REBOOT=REALLYSUPPRESS /qn

Upgrading in the default folder

1. Browse to the folder in which you have extracted the Dell Command | Configure installer from the Dell Update Package (DUP).
2. Run the following command: `msiexec.exe /i Command_Configure.msi /qn`

The Dell Command | Configure components are silently installed in the following locations:

- For 32-bit systems, C:\Program Files\Dell\Command Configure
- For 64-bit systems, C:\Program Files (x86)\Dell\Command Configure

Dell Command | Configure 4.10.1 for Windows Preinstallation Environment

Windows Preinstallation Environment (WinPe) provides a stand-alone preinstallation environment that is used to prepare a system for Windows installation. For client systems that do not have an operating system that is installed, you can create a bootable image that contains Dell Command | Configure to run the Dell Command | Configure commands on Windows PE. To create Windows PE 2.0 and 3.0 images, you can use Windows Automated Installation Kit (Windows AIK), and to create Windows PE 4.0, Windows PE 5.0, Windows PE 10.0, and Windows PE 11.0 images, you can use Windows Assessment and Deployment Kit (Windows ADK).

Using Windows PE 2.0, Windows PE 3.0, Windows PE 4.0, Windows PE 5.0, Windows PE 10.0, and Windows PE 11.0, you can integrate Dell Command | Configure.

Related links:


- Creating a bootable image PE using Windows PE 4.0, 5.0, 10.0, and 11.0
- Creating a bootable image PE using Windows PE 2.0 and 3.0

Topics:

- Creating a bootable image preinstallation environment using Windows PE 4.0, 5.0, 10.0, and 11.0
- Creating a bootable image preinstallation environment using Windows PE 2.0 and 3.0

Creating a bootable image preinstallation environment using Windows PE 4.0, 5.0, 10.0, and 11.0

- From the Microsoft website, download and install Windows ADK on the client system.

 **NOTE:** While installing select only **Deployment Tools** and **Windows Preinstallation Environment (Windows PE)**

- From [dell.com/support](https://www.dell.com/support), download and install Dell Command | Configure.
- Install Dell Command | Configure.
- Integrate the Dell Command | Configure directory structure into an ISO file to create a bootable ISO image.

Related Link:

- Integrating Dell Command | Configure directory structure into an ISO file using Windows PE 11.0
- Integrating Dell Command | Configure directory structure into an ISO file using Windows PE 10.0
- Integrating Dell Command | Configure directory structure into an ISO file using Windows PE 5.0
- Integrating Dell Command | Configure directory structure into an ISO file using Windows PE 4.0

Integrating the Dell Command | Configure directory structure into an ISO file using Windows PE 11.0

1. Install the Windows 11 operating system.
2. Download and install Windows ADK for Windows 11 operating system.
3. Create a Windows PE 11.0 image.

Related links:

- [Creating Windows PE 11.0 64-bit image](#)
- [Creating Windows PE 11.0 32-bit image](#)

Creating a Windows PE 11.0 64-bit image

1. Browse to C:\Program Files(x86)\Dell\Command Configure\X86_64.
2. Open the command prompt with administrator privileges.
3. Run the following command: cctk_x86_64_winpe_11.bat C:\winpe_x86_64 C:\Progra~2\Dell\Comman~1.
i NOTE: Ensure that the path that is used in the command is that of the Dell Command | Configure folder.
4. Browse to C:\winpe_x86\WIM and copy the ISO image.

Integrating the Dell Command | Configure directory structure into an ISO file using Windows PE 10.0

1. Install the Windows 10 operating system.
2. Download and install Windows ADK for Windows 10 operating system.
3. Create a Windows PE 10.0 image.

Related links:

- [Creating a Windows PE 10.0 64-bit image](#)
- [Creating a Windows PE 10.0 32-bit image](#)

Creating a Windows PE 10.0 64-bit image

1. Browse to C:\Program Files(x86)\Dell\Command Configure\X86_64.
2. Open the command prompt with administrator privileges.
3. Run the following command: cctk_x86_64_winpe_10.bat C:\winpe_x86_64 C:\Progra~2\Dell\Comman~1
i NOTE: Ensure that the path that is used in the command is that of the Dell Command | Configure folder.
4. Browse to C:\winpe_x86_64\WIM and copy the ISO image.

Creating a Windows PE 10.0 32-bit image

1. Browse to C:\Program Files\Dell\Command Configure\X86.
2. Open the command prompt with administrator privileges.
3. Run the following command: cctk_x86_winpe_10.bat C:\winpe_x86 C:\Progra~1\Dell\Comman~1.
i NOTE: Ensure that the path that is used in the command is that of the Dell Command | Configure folder.

4. Browse to C:\winpe_x86\WIM and copy the ISO image.


Integrating the Dell Command | Configure directory structure into an ISO file using Windows PE 5.0

1. Install the Windows 8.1 operating system.
2. Download and install Windows ADK for Windows 8.1 operating system.
3. Create a Windows PE 5.0 image.


Related links:

- [Creating Windows PE 5.0 64-bit image](#)
- [Creating Windows PE 5.0 32-bit image](#)

Creating a Windows PE 5.0 64-bit image

1. Browse to C:\Program Files(x86)\Dell\Command Configure\X86_64.
2. Open the command prompt with administrator privileges.
3. Run the following command: cctk_x86_64_winpe_5.bat C:\winpe_x86_64 C:\Progra~2\Dell\Comman~1.
 **NOTE:** Ensure that the path that is used in the command is that of the Dell Command | Configure folder.
4. Browse to C:\winpe_x86_64\WIM and copy the ISO image.

Creating a Windows PE 5.0 32-bit image

1. Browse to C:\Program Files\Dell\Command Configure\X86.
2. Open the command prompt with administrator privileges.
3. Run the following command: cctk_x86_winpe_5.bat C:\winpe_x86 C:\Progra~1\Dell\Comman~1.
 **NOTE:** Ensure that the path that is used in the command is that of the Dell Command | Configure folder.
4. Browse to C:\winpe_x86\WIM and copy the ISO image.

Integrating the Dell Command | Configure directory structure into an ISO file using Windows PE 4.0

1. Install the Windows 8 operating system.
2. Download and install Windows ADK for Windows 8.
3. Create a Windows PE 4.0 image.

Related Links:

- [Creating Windows PE 4.0 64-bit image](#)
- [Creating Windows PE 4.0 32-bit image](#)

Creating a Windows PE 4.0 64-bit image

1. Browse to C:\Program Files (x86)\Dell\Command Configure\X86_64.
2. Open the command prompt with administrator privileges.

3. Run the following command: cctk_x86_64_winpe_4.bat C:\winpe_x86_64 C:\Progra~2\Dell\Comman~1.

i NOTE: Ensure that the path that is used in the command is that of the Dell Command | Configure folder.

4. Browse to C:\winpe_x86_64\wim and copy the ISO image.

Creating a Windows PE 4.0 32-bit image

1. Browse to C:\Program Files\Dell\Command Configure\X86.
2. Open the command prompt with administrator privileges.
3. Run the following command: cctk_x86_winpe_4.bat C:\winpe_x86 C:\Progra~1\Dell\Comman~1.

i NOTE: Ensure that the path that is used in the command is that of the Dell Command | Configure folder.

4. Browse to C:\winpe_x86\WIM and copy the ISO image.

Creating a bootable image preinstallation environment using Windows PE 2.0 and 3.0

1. From the Microsoft website, download and install Windows AIK.
2. From dell.com/support, download and install Dell Command | Configure.
3. Download and install Dell Command | Configure.
4. Integrate the Dell Command | Configure directory structure into an ISO file (for Windows PE 2.0 and 3.0) to create a bootable ISO image.

Related Links:

- Integrating Dell Command | Configure directory structure to an ISO file using Windows PE 3.0
- Integrating Dell Command | Configure directory structure in a WIM file using Windows PE 2.0

Integrating Dell Command | Configure directory structure into an ISO file using Windows PE 3.0

Dell Command | Configure provides the cctk_x86_winpe_3.bat and cctk_x86_64_winpe_3.bat scripts that are must integrate

Dell Command | Configure . To integrate the Dell Command | Configure directory structure into an ISO file:

1. Browse to the directory where the script is located.

i NOTE: By default, the script for 32-bit systems is located in the Command Configure\x86 directory. The script for 64-bit systems is located in the Command Configure\x86_64 directory.

2. If you have installed AIK in a nondefault directory, open the script, set the AIKTOOLS path, and save the file. For example, Set AIKTOOLS=C:\WINAIK\Tools.
3. Run the script with the path where you want to create the ISO file and the Dell Command | Configure installation directory as two arguments.

i NOTE: Ensure that the directory that is specified for the ISO image is not an existing directory

- For a 32-bit system, run cctk_x86_winpe_3.bat C:\winPE_x86 C:\Progra~1\Dell\Comman~1.
- For a 64-bit system, run cctk_x86_64_winpe_3.bat C:\winPE_x86_64 C:\Progra~2\Dell\Comman~1.

i NOTE: Ensure that the path that is used in the command is that of the Command Configure folder.

The ISO image and the WIM file are created in the following folder.

- For a 32-bit system; C:\winPE_x86\WIM
- For a 64-bit system; C:\winPE_x86_64\WIM

Related Link: [Creating Windows PE 3.0 64-bit image](#)

Creating a Windows PE 3.0 64-bit image

1. Run cctk_x86_64_WinPE_3.bat C:\WinPE3_64bit C:\Progra~2\Dell\Comman~1

i **NOTE:** Ensure that the path that is used in the command is that of the Dell Command | Configure folder.

2. Browse to C:\WinPE3_64bit\WIM and burn the image.

Integrating the Dell Command | Configure directory structure into a WIM file using Windows PE 2.0

Dell Command | Configure provides the cctk_x86_winpe.bat and cctk_x86_64_winpe.bat scripts to integrate Dell Command | Configure into the WIM file. To integrate the Dell Command | Configure directory structure into a WIM file:

1. Browse to the directory where the script is located.

i **NOTE:** By default, the script for 32-bit systems is located at C:\Program Files\Dell\Command Configure\x86 directory. The script for 64-bit systems is located at Command Configure\x86_64 directory.

2. Run the appropriate script with the WIM file and Dell Command | Configure directory locations that are entered as two arguments: cctk_winpe.bat . If Dell Command | Configure is installed in the default directory, run the following script:

- For 32-bit system, cctk_x86_winpe.bat C:\winPE_x86 C:\Progra~1\Dell\Comman~1
- For 64-bit system, cctk_x86_64_winpe.bat C:\winPE_x86_64 C:\Progra~2\Dell\Comman~1

i **NOTE:** Ensure that the path that is used in the command is that of the Command Configure folder.

The files required to create the bootable ISO image and a WIM file -winpe.wim are created at the same location.

3. Rename the \winpe.wim file as boot.wim.
4. Overwrite the \ISO\sources\boot.wim file with the \boot.wim file. For example, copy C:\winPE_x86\boot.wim C:\winPE_x86\ISO\sources\boot.wim.
5. Create a bootable Windows PE image using Windows AIK.

Related Link:

- [Creating a bootable Windows PE image using Windows AIK](#)

Creating a bootable Windows PE image using Windows AIK

1. Click **Start > Programs > Microsoft Windows AIK > Windows PE Tools Command Prompt**

i **NOTE:** To prepare a bootable image for a 64-bit supported system, from the command prompt, browse to the following directory:

- For 64-bit system; \Windows AIK\Tools\amd64

- For 32-bit system; \Windows AIK\Tools\i86
Otherwise, \Windows AIK\Tools\PEtools
2. Run the command: `oscdimg -n -b\etfsboot.com \ISO <path_of_wim_file\image_file_name.iso>`.
For example, `oscdimg -n -bc:\winPE_x86\etfsboot.com c:\winPE_x86\ISO c:\winPE_x86\WinPE2.0.iso`.
This command creates a bootable ISO image, WinPE2.0.iso, in the path C:\winPE_x86 directory.

References for Dell Command | Configure

In addition to this guide, you can access the following guides available at dell.com/support:

- Dell Command | Configure User's Guide
- Dell Command | Configure Command Line Interface Reference Guide

Topics:

- Accessing documents from the Dell support site

Accessing documents from the Dell support site

You can access the required documents by selecting your product.

1. Go to dell.com/support.
2. Click **Browse all products**, click **Software**, and then click **Client Systems Management**.
3. To view the required documents, click the required product name and version number.

Documents / Resources

	DELL Command, Configure [pdf] Installation Guide Version 4.10.1, Command Configure, Command, Configure
---	---

References

-  [Support | Dell US](#)