


# FUJITSU SnapCenter Plug-in for Microsoft SQL Server User Guide

[Home](#) » [FUJITSU](#) » FUJITSU SnapCenter Plug-in for Microsoft SQL Server User Guide 



**SnapCenter Software 4.4**  
**Quick Start Guide**  
**For SnapCenter Plug-in for Microsoft SQL Server**  
**User Guide**



## Contents

- [1 SnapCenter Plug-in for Microsoft SQL Server](#)
- [2 Preparing for installation](#)
- [3 Installing SnapCenter Server](#)
- [4 Installing the Plug-in for Microsoft SQL Server](#)
- [5 Where to find additional information](#)
- [6 Documents / Resources](#)
- [7 Related Posts](#)

## SnapCenter Plug-in for Microsoft SQL Server

SnapCenter consists of the SnapCenter Server and SnapCenter plug-ins. This Quick Start Guide is a condensed set of installation instructions for installing the SnapCenter Server and the SnapCenter Plug-in for Microsoft SQL Server. For more details, see the [SnapCenter Installation and Setup Guide](#).

## Preparing for installation

### Domain and workgroup requirements

SnapCenter Server can be installed on systems that are either in a domain or in a workgroup.

If you are using an Active Directory domain, you should use a Domain user with local administrator rights. The Domain user should be a member of the local Administrator group on the Windows host. If you are using workgroups, you should use a local account that has local administrator rights.

### Licensing requirements

The type of licenses you install depends on your environment.

License	Where required
SnapCenter Standard controller-based	Required for ETERNUS HX or ETERNUS AX controllers SnapCenter Standard license is a controller-based license and is included as part of the premium bundle. If you have the SnapManager Suite license, you also get the SnapCenter Standard license entitlement. If you want to install SnapCenter on a trial basis with ETERNUS HX or ETERNUS AX, you can obtain a Premium Bundle evaluation license by contacting the sales representative.
SnapMirror or SnapVault	ONTAP Either SnapMirror or SnapVault license is required if replication is enabled in Snap Center.

License	Where required
SnapCenter Standard licenses (optional)	<p>Secondary destinations</p> <p><b>Note:</b> It is recommended, but not required, that you add Snap Center Standard licenses to secondary destinations. If Snap Center Standard licenses are not enabled on secondary destinations, you cannot use Snap Center to backup resources on the secondary destination after performing a failover operation.</p> <p>However, a FlexClone license is required on secondary destinations to perform clone and verification operations.</p>

### Additional requirements

Storage and applications	Minimum requirements
ONTAP and application plug-in	Contact Fujitsu support personnel.

Hosts	Minimum requirements
Operating System (64-bit)	Contact Fujitsu support personnel.
CPU	<ul style="list-style-type: none"> <li>· Server host: 4 cores</li> <li>· Plug-in host: 1 core</li> </ul>
RAM	<ul style="list-style-type: none"> <li>· Server host: 8 GB</li> <li>· Plug-in host: 1 GB</li> </ul>
Hard drive space	<ul style="list-style-type: none"> <li>· Server host: <ul style="list-style-type: none"> <li>o 4 GB for SnapCenter Server software and logs</li> <li>o 6 GB for SnapCenter repository</li> </ul> </li> <li>· Each plug-in host: 2 GB for plug-in installation and logs, this is required only if plug-in is installed on a dedicated host.</li> </ul>
Third-party libraries	<p>Required on SnapCenter Server host and plug-in host:</p> <ul style="list-style-type: none"> <li>· Microsoft .NET Framework 4.5.2 or later</li> <li>· Windows Management Framework (WMF) 4.0 or later</li> <li>· PowerShell 4.0 or later</li> </ul>
Browsers	Chrome, Internet Explorer, and Microsoft Edge

Port type	Default port
SnapCenter port	8146 (HTTPS), bidirectional, customizable, as in the URL <a href="https://server.8146">https://server.8146</a>
SnapCenter SMCore communication port	8145 (HTTPS), bidirectional, customizable

Port type	Default port
Repository database	3306 (HTTPS), bidirectional
Windows plug-in hosts	135, 445 (TCP) In addition to ports 135 and 445, the dynamic port range specified by Microsoft should also be open. Remote install operations use the Windows Management Instrumentation (WMI) service, which dynamically searches this port range. For information on the dynamic port range supported, see <a href="#">Microsoft Support Article 832017: Service overview and network port requirements for Windows.</a>
SnapCenter Plug-in for Windows	8145 (HTTPS), bidirectional, customizable
ONTAP cluster or SVM communication port	443 (HTTPS), bidirectional 80 (HTTP), bidirectional The port is used for communication between the SnapCenter Server host, plug-in host, and SVM or ONTAP Cluster.

## Snap Center Plug-in for Microsoft SQL Server requirements

- You should have a user with local administrator privileges with local login permissions on the remote host. If you manage cluster nodes, you need a user with administrative privileges to all the nodes in the cluster.
- You should have a user with sysadmin permissions on the SQL Server. The plug-in uses Microsoft VDI Framework, which requires sysadmin access.
- If you were using SnapManager for Microsoft SQL Server and want to import data from SnapManager for Microsoft SQL Server to SnapCenter, see the [SnapCenter Installation and Setup Guide](#).

## Installing SnapCenter Server

### Downloading and installing SnapCenter Server

1. Download the SnapCenter Server installation package from the DVD included with the product and then double-click the exe.  
After you initiate the installation, all the prechecks are performed and if the minimum requirements are not met appropriate error or warning messages are displayed. You can ignore the warning messages and proceed with installation; however, errors should be fixed.
2. Review the pre-populated values required for the SnapCenter Server installation and modify if required.  
You do not have to specify the password for MySQL Server repository database. During SnapCenter Server installation the password is auto generated.  
**Note:** The special character “%” is not supported in the custom path for installation. If you include “%” in the

path, installation fails.

3. Click Install Now.

## **Logging in to Snap Center**

1. Launch SnapCenter from a shortcut on the host desktop or from the URL provided by the installation (<https://server.8146> for default port 8146 where SnapCenter Server is installed).
2. Enter the credentials. For a built-in domain admin username format, use: NetBIOS\<username> or <username>@<domain> or <DomainFQDN>\<username>. For a built-in local admin username format, use <username>.
3. Click Sign In.

## **Adding SnapCenter licenses**

### **Adding a SnapCenter Standard controller-based license**

1. Log in to the controller using the ONTAP command line and enter: system license add – license-code <license\_key>
2. Verify the license: license show

### **Adding a SnapCenter capacity-based license**

1. In the SnapCenter GUI left pane, click Settings > Software, and then in the License section, click +.
2. Select one of two methods for obtaining the license: either enter your Fujitsu Support Site login credentials to import licenses or browse to the location of the Fujitsu License File and click Open.
3. On the Notifications page of the wizard, use the default capacity threshold of 90 percent.
4. Click Finish.

## **Setting up storage system connections**

1. In the left pane, click Storage Systems > New.
2. In the Add Storage System page, perform the following:
  - a) Enter the name or IP address of the storage system.
  - b) Enter the credentials that are used to access the storage system.
  - c) Select the check boxes to enable Event Management System (EMS) and AutoSupport.
3. Click More Options if you want to modify the default values assigned to platform, protocol, port, and timeout.
4. Click Submit.

## **Installing the Plug-in for Microsoft SQL Server**

### **Setting up Run As Credentials**

1. In the left pane, click Settings > Credentials > New.
2. Enter the credentials. For a built-in domain admin username format, use: NetBIOS\<username> or <username>@<domain> or <DomainFQDN>\<username>. For a built-in local admin username format, use

<username>.

## Adding a host and installing the Plug-in for Microsoft SQL Server

1. In the SnapCenter GUI left pane, click Hosts > Managed Hosts > Add.
2. On the Hosts page of the wizard, perform the following:
  - a. Host Type: Select Windows host type.
  - b. Host name: Use the SQL host or specify the FQDN of a dedicated Windows host.
  - c. Credentials: Select the valid credential name of the host that you created or create new credentials.
3. In the Select Plug-ins to Install section, select Microsoft SQL Server.
4. Click More Options to specify the following details:
  - a. Port: Either retain the default port number or specify the port number.
  - b. Installation Path: The default path is C:\Program Files\Fujitsu\SnapCenter. You can optionally customize the path.
  - c. Add all hosts in the cluster: Select this check box if you are using SQL in WSFC.
  - d. Skip preinstall checks: Select this check box if you already installed the plug-ins manually or you do not want to validate whether the host meets the requirements for installing the plugin.
5. Click Submit.


## Where to find additional information

- [Snap Center Installation and Setup Guide](#) for additional information on SnapCenter Server and plug-in installation.



Copyright 2021 FUJITSU LIMITED. All rights reserved.  
SnapCenter Software 4.4 Quick Start Guide

## Documents / Resources

	<p><a href="#">FUJITSU SnapCenter Plug-in for Microsoft SQL Server</a> [pdf] User Guide SnapCenter Plug-in for Microsoft SQL Server, Microsoft SQL Server, SnapCenter Plug-in, SQL Server, Plug-in</p>
---	--