

# JUNIPER NETWORKS 9.1R2 CTP View Management System Software User Guide

Home » JUNIPER NETWORKS » JUNIPER NETWORKS 9.1R2 CTP View Management System Software User Guide ₺

## JUNIPER NETWORKS 9.1R2 CTP View Management System Software

#### **Contents**

- 1 Release 9.1R2 December 2020
- 2 Installing CTP View 9.1R2
- 3 Change password of Default User accounts
- 4 Table 2: Critical or Important CVEs Included in php
- **5 Customer Support**
- 6 Documents / Resources
  - **6.1 References**
- **7 Related Posts**



These release notes accompany Release 9.1R2 of the CTP View Management System software. They contain install information and describe the enhancements to the software. The CTP View Release 9.1R2 software is compatible with Juniper Networks CTP series platforms running CTPOS version 9.1R2 or earlier.

You can find these release notes on the Juniper Networks CTP Software Documentation webpage, which is located at <a href="https://www.juniper.net/documentation/product/en">https://www.juniper.net/documentation/product/en</a> US/ctpview

#### **Release Highlights**

The following features or enhancements have been added to CTP View Release 9.1R2.

- [PR 1364238] STIG hardening for CTP View 9.1R2.
- [PR 1563701] Enable serial console by default when CTP View is installed on a Centos 7 physical server.

**NOTE:** CTP View 9.1R2 runs on an updated OS (CentOS 7.5.1804) which provides better security with improved resilience and robustness.

The following features are not supported in CTP View Release 9.1R2.

- [PR 1409289] PBS and L2Agg features are not supported. These features will be reintroduced in a future release.
- [PR 1409293] VCOMP bundle and Coops analog voice bundle features are not supported. These features 1will be reintroduced in a future release.

## Resolved Issues in CTP View Release 9.1R2

The following issues have been resolved in CTP View Release 9.1R2:

• [PR 1468711] CTP View 9.1R2 requires users to change the default password of default user accounts.

#### **Known Issues in CTP View Release 9.1R2**

None.

#### **Required Install Files**

It is your responsibility to install CentOS on a VM, and the CentOS version must be 7.5.1804 (<a href="http://vault.centos.org/7.5.1804/isos/x86\_64/">http://vault.centos.org/7.5.1804/isos/x86\_64/</a>). For information on how to create a CentOS 7 virtual machine, see "Creating a CentOS 7 Virtual Machine" on page 3. Installing newer releases of Centos are not supported you must use Centos 7.5.1804. If you have queries or need further assistance, contact Juniper Networks Technical Assistance Center (JTAC).

Following file is provided for installing the CTP View software:

File	Filename	Checksum
Software and CentOS OS Updates	CTPView-9.1R-2.0-1.el7.x86_64.rpm	5e41840719d9535aef17ba275b5b6343

Use the following information to determine the correct file to use:

CTP View Server OS	Installed CTP View Release	File for Upgrade	Server Reboot s During Upgr ade?
CentOS 7.5	NA	CTPView-9.1R-2.0-1.el7.x86_64.rpm	Yes

Recommended System Configuration for Hosting a CTP View Server

The following are the recommended hardware configuration to setup a CTP View 9.1R2 server:

- CentOS 7.5.1804 (64-bit)
- 1x processor (4 cores)
- 4 GB RAM
- Number of NICs 2
- 80 GB Disk space

#### **CTP View Installation and Maintenance Policy**

From the release of CTP View 9.0R1, Juniper Networks has adopted a new policy for installation and maintenance of the CTP View server. CTP View is now being distributed as an "Application only" product, in the form of an RPM package. You can now install and maintain the OS (CentOS 7.5) according to the guidelines described in "Installing CTP View 9.1R2" on page 8. With the CTP View 7.3Rx and earlier releases, the OS (CentOS 5.11) and CTP View application were combined and distributed as a single installation ISO, and all updates (OS and CTP View application) were only available from Juniper Networks. This causes a delay in getting CTP View maintenance releases for important security updates (including Linux OS applications and CTP View application).

With this new model, you can update individual CentOS applications independently from the CTP View application if any security vulnerabilities are reported for the Linux OS applications. This provides more flexibility you need to ensure the security of your Linux-based platforms.

CTP View is made up of:

- Type 1—Stock CentOS 7.5 RPMs
- Type 2—Stock CentOS RPMs from other CentOS versions
- Type 3—Modified CentOS RPMs
- Type 4—CTP View application file

Where, "Stock" RPMs are the packages that are associated with a particular release of CentOS and readily available on the Internet. "Modified" RPMs are stock versions of RPMs that are modified by Juniper Networks for the needs of the CTP View platform. The CentOS 7.5 installation ISO only contains the components of type 1. The monolithic CTP View RPM contains the remaining components of types 2, 3, and 4, which can be unpacked and

installed.

When Juniper Networks delivers a CTP View maintenance release RPM, it contains the updated component versions of types 2, 3, and 4. It also contains dependencies to make sure that type 1 components are also up to date and warn the user if any of them need to be updated.

Juniper Networks maintains a list of RPMs for CTP View that we suggest to be upgraded for security and functional reasons. The following methods are used for determining which CTP View RPMs need updates:

- Regular Retina/Nessus sc0ans
- Notifications from Juniper's SIRT team
- Reports from customers

When an RPM update is required, Juniper Networks validates the new version of the component to make sure that it functions properly before adding it to the RPM list. This list will be shared to you via a KB. Although CTP View maintenance updates mandate (and possibly provide) up-to-date RPMs before installation, this RPM list helps you to update your CTP View software between releases. If there is an RPM added to the RPM list, you can take immediate action. Juniper Networks delivers the components of type 3 via maintenance releases only.

For type 1 and 2 components, the RPMs should be freely available on the web, and Juniper Networks provides sample links. If you discover that an RPM needs a security update and it is not in the RPM list, you can notify us so that we can test it and add it to the list.

**CAUTION:** A bulk RPM update using "yum update" is strictly forbidden. CTP View 9.x, although mainly based on CentOS 7.5, is also made up of RPMs from other distributions. Performing an update to the latest version of CentOS 7 may cause CTP View to be non-functional, and a reinstallation may be required.

If you update RPMs that are not on the KB RPM list, CTP View may not function properly.

#### **Creating a Centos 7 Virtual Machine**

Before you begin:

• Make sure that vSphere client is installed on your workstation.

**NOTE:** Within vSphere, there are numerous ways to perform a particular task. The following example illustrates one such method. You can use the procedure that suits your network deployment effectively.

To create a new CentOS 7 Sting's VM instance of CTP View server on an Essig Server:

- 1. Copy the CentOS 7 ISO file (centOS-7-x86\_64-DVD-1804.iso) to the Essig datastore. The CentOS 7 ISO can be downloaded from http://vault.centos.org/7.5.1804/isos/x86\_64/.
- 2. Start the vSphere client and enter the ESXi server IP address and your login credentials.
- 3. Start the wizard to create a new virtual machine. Select File > New > Virtual Machine.
- 4. Select the configuration as Typical and click Next.
- 5. Enter a name for the VM. For example, CTPView\_9.1R2.
- 6. Select the datastore (with at least 80 GB free space) and click Next.
- 7. Select Guest OS as Linux and version as Other Linux (64-bit), and then click Next.
- 8. Select the number of NICs as 2 and adapter type as E1000, and then click Next.


- 9. Select the virtual disk size as 80 GB and select Thick Provision Lazy Zeroed.
- 10. Select the Edit the virtual machine settings before completion check box and click Continue.
- 11. Click the Hardware tab and select memory size as 4 GB.
- 12. In the Hardware tab, select CPU. Then, select the number of virtual sockets as 2 and number of cores per socket as 1 (you can select up to 4 cores).
- 13. In the Hardware tab, select CD/DVD. Then, select the device type as Datastore ISO File and browse to CentOS 7 ISO file. Select the Connect at power on check box under Device Status.
- 14. Click Finish.
- 15. Select your created virtual machine in the left panel of vSphere > Inventory.
- 16. In the Getting Started tab, select Power on the virtual machine.
- 17. Switch to the Console tab and click inside the terminal emulator.
- 18. Select the Install CentOS Linux 7 option with the Up-Arrow key and press Enter.




- 19. Press the Enter key to begin the installation process.
- 20. Select the language and your desired country time zone (if necessary) and then click Continue.
- 21. Click the SOFTWARE SELECTION option.




22. In the Basic Environment section, select the Basic Web Server radio button. In the Add-Ons for Selected Environment section, select PHP Support and Perl for Web check boxes and click Done.




- 23. Click INSTALLATION DESTINATION and verify that the VMware Virtual disk (80 GB) is selected.
- 24. In the Other Storage Options section, select the I will configure a partitioning option button.



25. Click Done. The MANUAL PARTITIONING page appears.



- 26. Click the + button. The ADD A NEW MOUNT POINT dialog box appears. Juniper Business Use Only
- 27. To create a partition for /boot, enter /boot in the Mount Point field and enter 1014 MB in the Desired Capacity field. Then, click Add mount point.



- 28. Select Standard Partition from the Device Type list and select ext3 from the File System list. Enter LABEL=/ boot in the Label field and then click Update Settings.
- 29. Similarly, repeat the steps 26 through 28 to create partitions for the following mount points with the provided settings.


**Table 1: Mount Points and Their Settings** 

Mount Point	Desired Capacity	Device Type	File System	Label
/tmp	9.5 GB	Standard Partition	ext3	LABEL=/tmp
/	8 GB	Standard Partition	ext3	LABEL=/
/var/log	3.8 GB	Standard Partition	ext3	LABEL=/var/log
/var	3.8 GB	Standard Partition	ext3	LABEL=/var
/var/log/audit	1.9 GB	Standard Partition	ext3	LABEL=/var/log/a
/home	1.9 GB	Standard Partition	ext3	LABEL=/home
/var/www	9.4 GB	Standard Partition	ext3	LABEL=/var/www


30. Click Done twice and then click Accept Changes.



- 31. Click NETWORK & HOST NAME.
- 32. Select an Ethernet option (for example, Ethernet (ens32)), enter the hostname (for example, ctp view) in the Host name field, and then click Apply.



33. Click Configure. Then, click the IPv4 Settings tab.



- 34. Select Manual from the Method list and click Add.
- 35. Enter values for Address, Netmask, and Gateway fields, and then click Save.
- 36. Click the toggle button in the right-top corner to bring the configured Ethernet up and running, and then click Done.
- 37. Click SECURITY POLICY.
- 38. Select the DISA STIG for CentOS Linux 7 Server option and click Select Profile. Then, click Done.
- 39. Click Begin Installation. The USER SETTINGS page appears.
- 40. Click USER CREATION, enter the username as "admin", and enter a password. Please don't enter username as "junipers" here.



- 41. Select the Make this user administrator check box and click Done.
- 42. In the USER SETTINGS page, click ROOT PASSWORD, enter the password as "CTPView-2-2" or any other password and click Done.
- 43. After the installation process is completed, click Reboot.

## **Installing CTP View 9.1R2**

CTP View can be installed on the newly created CentOS 7.5[1804] VM or CentOS 7.5[1804] bare metal server.

Steps are as follows:

- 1. Create a new CentOS 7 Virtual Machine (VM) instance as mentioned in "Creating a Centos 7 Virtual Machine" on page 3.
- 2. Copy the CTP View RPM (CTPView-9.1R-2.0-1.el7.x86\_64.rpm) to /tamp directory of the newly created CentOS 7.5[1804] VM or CentOS 7.5[1804] bare metal.
- 3. Login as "admin" user that you created at the time of creating Centos 7 VM. Install CTP View RPM. If installing on top of
  - Centos 7 or 9.1R1 use command "sudor rpm -Urho CTPView-9.1R-2.0-1.el7.x86\_64.rpm"

- 9.0R1 use command "sudor rpm -Usha -force CTPView-9.1R-2.0-1.el7.x86\_64.rpm".
- 4. Change the passwords for all the default user accounts (junipers, root, Juniper, ctpview\_pgsql) at the end during upgrade (Refer section Change password of Default User accounts).

## Change password of Default User accounts

This step is applicable only when you install CTPView 9.1R2 RPM on your server. Change the passwords for all the default user accounts as shown below:

CTP View has been installed on your system. Now, You need to set the passwords for all the default user accounts.

PLEASE REMEMBER THESE PASSWORDS!!!

Password recovery is not a simple process:

- It is service affecting.
- · It requires console access to the CTP View
- It requires rebooting the CTP View (Possibly even a system repower)

The new password must be alphanumeric or the characters

The new password must also be at least 6 characters long, with

1 lowercase, 1 uppercase, 1 digits and 1 other characters.

Note: If unique passwords are not required, use "CTPView-2-2"

Enter New UNIX Password for root

Retype New UNIX Password for root

Changing password for user root.

passwd: all authentication tokens updated successfully.

This will be a System Administrator

The new password must be alphanumeric or the characters

The new password must also be at least 6 characters long, with\ 1 lowercase, 1 uppercase, 1 digits and 1 other characters.

Note: If unique passwords are not required, use "CTPView-2-2"

Enter New UNIX Password for juniper\_sa

Retype New UNIX Password for juniper\_sa

Changing password for user junipers. passwd: all authentication tokens updated successfully. The new password must be alphanumeric or the characters

The new password must also be at least 6 characters long, with

1 lowercase, 1 uppercase, 1 digits and 1 other characters.

Note: If unique passwords are not required, use "CTPView-2-2" Changing password for user Juniper Enter the new password:

Re-Enter the new password:

You will now be asked for the password of the PostgreSQL Administrator account:

Password for user postures:

==== Successfully updated the CTP View password for default user Juniper. =====

**Note:** The user Juniper has been assigned to the default user group TempGroup and has been given default user properties. Review the values using the CTPView Admin Center and make any appropriate modifications.

The new password must be alphanumeric or the characters

The new password must also be at least 6 characters long, with

1 lowercase, 1 uppercase, 1 digits and 1 other characters.

Note: If unique passwords are not required, use "CTPView-2-2" Changing password for user ctpview\_pgsql

Enter the new password:

Re-Enter the new password:

You will now be asked for the password of the PostgreSQL Administrator account:

Password for user postures:

Note – You can also reset the password of all default user accounts from CTP View menu -> Advanced Functions -> Reset account for default System Administrator

**Uninstalling CTPView 9.1R2** 

CTP View 9.1R2 can be uninstalled from Centos 7 by performing the following steps:

- 1. Check if root login is permitted. If not, enable root login from menu -> Security Profile(1) -> Modify Security Level(5) -> Set OS level to 'very-low'(3).
- 2. Login via "root" user and run the command "sudo rpm -edh CTPView-9.1R-2.0-1.el7.x86\_64".
- 3. System will reboot after uninstalling, use user (the one you created while creating CentOS 7) to login.

CVEs and Security Vulnerabilities Addressed in CTP View Release 9.1R2

The following tables list the CVEs and security vulnerabilities that have been addressed in CTP View 9.1R2. For more information about individual CVEs, see <a href="http://web.nvd.nist.gov/view/vuln/search">http://web.nvd.nist.gov/view/vuln/search</a>.

Table 2: Critical or Important CVEs Included in php

CVE-2018-10547	CVE-2018-5712	CVE-2018-7584	CVE-2019-9024
----------------	---------------	---------------	---------------

Table 3: Critical or Important CVEs Included in kernel

CVE-2019-14816	CVE-2019-14895	CVE-2019-14898	CVE-2019-14901
CVE-2019-17133	CVE-2019-11487	CVE-2019-17666	CVE-2019-19338
CVE-2015-9289	CVE-2017-17807	CVE-2018-19985	CVE-2018-20169
CVE-2018-7191	CVE-2019-10207	CVE-2019-10638	CVE-2019-10639
CVE-2019-11190	CVE-2019-11884	CVE-2019-12382	CVE-2019-13233
CVE-2019-13648	CVE-2019-14283	CVE-2019-15916	CVE-2019-16746
CVE-2019-18660	CVE-2019-3901	CVE-2019-9503	CVE-2020-12888
CVE-2017-18551	CVE-2018-20836	CVE-2019-9454	CVE-2019-9458
CVE-2019-12614	CVE-2019-15217	CVE-2019-15807	CVE-2019-15917
CVE-2019-16231	CVE-2019-16233	CVE-2019-16994	CVE-2019-17053
CVE-2019-17055	CVE-2019-18808	CVE-2019-19046	CVE-2019-19055
CVE-2019-19058	CVE-2019-19059	CVE-2019-19062	CVE-2019-19063
CVE-2019-19332	CVE-2019-19447	CVE-2019-19523	CVE-2019-19524
CVE-2019-19530	CVE-2019-19534	CVE-2019-19537	CVE-2019-19767
CVE-2019-19807	CVE-2019-20054	CVE-2019-20095	CVE-2019-20636
CVE-2020-1749	CVE-2020-2732	CVE-2020-8647	CVE-2020-8649
CVE-2020-9383	CVE-2020-10690	CVE-2020-10732	CVE-2020-10742
CVE-2020-10751	CVE-2020-10942	CVE-2020-11565	CVE-2020-12770
CVE-2020-12826	CVE-2020-14305	CVE-2019-20811	CVE-2020-14331

Table 4: Critical or Important CVEs Included in net-snmp

CVE-2018-18066

## Table 5: Critical or Important CVEs Included in nss, nspr

CVE-2019-11729	CVE-2019-11745	CVE-2019-11719	CVE-2019-11727
CVE-2019-11756	CVE-2019-17006	CVE-2019-17023	CVE-2020-6829
CVE-2020-12400	CVE-2020-12401	CVE-2020-12402	CVE-2020-12403

## Table 6: Critical or Important CVEs Included in python

CVE-2018-20852	CVE-2019-16056	CVE-2019-16935	CVE-2019-20907
	l .		

## Table 7: Critical or Important CVEs Included in OpenSSL

CVE-2016-2183

## Table 8: Critical or Important CVEs Included in sudo

CVE-2019-18634

## Table 9: Critical or Important CVEs Included in rsyslog

CVE-2019-18634

## Table 10: Critical or Important CVEs Included in http

CVE-2017-15710	CVE-2018-1301	CVE-2018-17199
CVE-2017-15715	CVE-2018-1283	CVE-2018-1303
CVE-2019-10098	CVE-2020-1927	CVE-2020-1934

## Table 11: Critical or Important CVEs Included in unzip

CVE-2019-13232

## Table 12: Critical or Important CVEs Included in bind

CVE-2018-5745	CVE-2019-6465	CVE-2019-6477	CVE-2020-8616
CVE-2020-8617	CVE-2020-8622	CVE-2020-8623	CVE-2020-8624

## Table 13: Critical or Important CVEs Included in curl

CVE-2019-5436	CVE-2019-5482	CVE-2020-8177
---------------	---------------	---------------

## Table 14: Critical or Important CVEs Included in rigidi

CVE-2019-18397

## Table 15: Critical or Important CVEs Included in expat

CVE-2018-20843	CVE-2019-15903		
Table 16: Critical or Important CVEs Included in glib2			
CVE-2019-12450	CVE-2019-14822		
Table 17: Critical or Important CVEs Included in lipping			
CVE-2017-12652			
Table 18: Critical or Important CVEs Included in poi			
CVE-2019-14866			
Table 19: Critical or Important CVEs Included in e2fsprog	ys		
CVE-2019-5094	CVE-2019-5188		
Table 20: Critical or Important CVEs Included in retype			
CVE-2020-15999			
Table 21: Critical or Important CVEs Included in Hun spell			
CVE-2019-16707			
Table 22: Critical or Important CVEs Included in libX11			
CVE-2020-14363			
Table 23: Critical or Important CVEs Included in libcroco			
CVE-2020-12825			
Table 24: Critical or Important CVEs Included in libssh2			

Table 25: Critical or Important CVEs Included in open dap

CVE-2019-17498

CVE-2020-12243

Table 26: Critical or Important CVEs Included in dbus

Table 27: Critical or Important CVEs Included in glibc

CVE-2019-19126

CVE-2019-12749

Table 28: Critical or Important CVEs Included in system

CVE-2019-20386

#### **CTP Documentation and Release Notes**

For a list of related CTP documentation, see

#### https://www.juniper.net/documentation/product/en US/ctpview

If the information in the latest release notes differs from the information in the documentation, follow the CTPOS Release Notes and the CTP View Server Release Notes.

To obtain the most current version of all Juniper Networks technical documentation, see the product documentation page on the Juniper Networks website at <a href="https://www.juniper.net/documentation/">https://www.juniper.net/documentation/</a>

#### **Requesting Technical Support**

Technical product support is available through the Juniper Networks Technical Assistance Center (JTAC). If you are a customer with an active J-Care or JNASC support contract, or are covered under warranty, and need post sales technical support, you can access our tools and resources online or open a case with JTAC.

- JTAC policies—For a complete understanding of our JTAC procedures and policies, review the JTAC User Guide located at <a href="https://www.juniper.net/us/en/local/pdf/resource-guides/7100059-en.pdf">https://www.juniper.net/us/en/local/pdf/resource-guides/7100059-en.pdf</a>.
- Product warranties—For product warranty information, visit- <a href="https://www.juniper.net/support/warranty/">https://www.juniper.net/support/warranty/</a>
- JTAC hours of operation—The JTAC centers have resources available 24 hours a day, 7 days a week, 365 days a year.

#### **Revision History**

December 2020—Revision 1, CTPView Release 9.1R2

#### **Customer Support**

Copyright © 2020 Juniper Networks, Inc. All rights reserved.

Juniper Networks, the Juniper Networks logo, Juniper, and Junos are registered trademarks of Juniper Networks, Inc. and/or its affiliates in the United States and other countries. All other

trademarks may be property of their respective owners.

Juniper Networks assumes no responsibility for any inaccuracies in this document. Juniper Networks reserves the right to change, modify, transfer, or otherwise revise this publication without notice.

#### **Documents / Resources**



<u>JUNIPER NETWORKS 9.1R2 CTP View Management System Software</u> [pdf] User Guide 9.1R2 CTP View Management System, 9.1R2, CTP View Management System, View Management System, Wanagement System

#### References

- © Index of /7.5.1804/isos/x86\_64
- NVD Search and Statistics
- **J** <u>Documentation | Juniper Networks</u>
- User Manual

#### Manuals+, Privacy Policy

This website is an independent publication and is neither affiliated with nor endorsed by any of the trademark owners. The "Bluetooth®" word mark and logos are registered trademarks owned by Bluetooth SIG, Inc. The "Wi-Fi®" word mark and logos are registered trademarks owned by the Wi-Fi Alliance. Any use of these marks on this website does not imply any affiliation with or endorsement.