

# **Certificates for Cisco Identity Service Instructions**

Home » Cisco » Certificates for Cisco Identity Service Instructions





#### **Contents**

- 1 Certificates for Cisco Identity Service
- 2 Export Cisco Identity Service Certificates
- **3 Import Cisco IdS Certificates**
- 4 Documents / Resources
- **5 Related Posts**

## **Certificates for Cisco Identity Service**

- Export Cisco Identity Service Certificates, on page 1
- Import Cisco IdS Certificates, on page 1

## **Export Cisco Identity Service Certificates**

**Step 1** Sign in to Cisco Unified Operating System Administration on the Cisco IdS server using the following URL: https://hostname of Cisco IdS server: 8443/cmplatform.

Step 2 Select Security > Certificate Management.

Step 3 Enter the search criteria as tomcat-trust and then click Find to filter the certificate.

The tomcat-trust certificates list is displayed. If you do not find the tomcat certificate for your server in the Certificate List, then click Generate Self-signed. When the certificate generation is complete, reboot your server. Then restart this procedure. For more information on generating the self-signed certificate, see Cisco Unified Operating System Administration Online Help.

**Step 4** Click the tomcat-trust certificate hyperlink in the Common Name column. The tomcat Certificate Details dialog box is displayed.

Step 5 Click Download .PEM File.

Step 6 Save the .PEM file in your local machine.

#### What to do next

Perform the same steps for both the primary and secondary Finesse nodes.

Import the Cisco IdS certificates into the Finesse trust store as tomcat-trust.

## **Import Cisco IdS Certificates**

**Step 1** Sign in to Cisco Unified Operating System Administration on the Finesse server using the following URL: https://FQDNof Finesse server: 8443/cmplatform.

**Step 2** Select Security > Certificate Management > Upload Certificate/Certificate chain.

Step 3 From the Certificate Purpose drop-down list, select tomcat-trust.

**Step 4** In the Upload File field, click Choose File and browse to the tomcat.pem file that you saved on your system.


Step 5 Click Upload.

Step 6 Reboot the Cisco Finesse node.

**Note** Perform the same steps for both the primary and secondary Finesse nodes.



### **Documents / Resources**



Manuals+,