



SEAGATE LYVE Cloud User Guide

[Home](#) » [Seagate](#) » **SEAGATE LYVE Cloud User Guide** [PDF](#)



Contents

- [1 Get Connected](#)
- [2 Create Lyve Cloud Account](#)
- [3 Connect with Cyberduck](#)
- [4 Documents / Resources](#)
 - [4.1 References](#)
 - [5 Related Posts](#)

Get Connected


Lyve Cloud is an S3 – compatible storage as a service built for scalable backups, frictionless archival, and big-data analytics to support any sized workload. Lyve Cloud's flexible backend protected with Equinix's Tier 4 data center defense makes connecting to any multi-cloud environment secure and efficient.

Lyve Cloud's S3 compatible application programming interface (API) enables enterprises to easily connect to Lyve Cloud. S3 compatibility enables access to Lyve Cloud from any public or private internet service provider. After connecting to Lyve Cloud and the customer account is created, customers can follow these three simple steps to get started.

Create Lyve Cloud Account


Step 1: Create Bucket

Go to the "Bucket" section of the Lyve Cloud Console and select the "Create Bucket" button.



Step 2: Create Bucket Permission

Go to the “Permissions” section of the Lyve Cloud Console and select the “Create Bucket Permission” button.



Step 3: Create Service Accounts

Go to the “Service Accounts” section of the Lyve Cloud Console and select the “Create Service Account” button.

For more information on how to create a bucket, consult the Lyve Cloud Quick Start Guide or view the Tutorial Videos.

Connect with Cyberduck

As a reminder, consult your organization's policies and the EULA policies of the software before downloading 3rd party applications.

Connection Instructions: Please complete these steps in order.

Step 1: Copy the Server address in Lyve Cloud Select Buckets / Select the Bucket Name

Name	Region	Usage	Created On	Status
Lyve Cloud	US - Virginia (US-E...)	0B	2022-02-21	Logged

Step 2: Select 'Copy S3 endpoint' and save the address. This is the Server address. You will use this in step 6.

LYVE CLOUD™

Home Marketplace NEW

STORAGE

Buckets Permissions Service Accounts

IDENTITY & ACCESS

Users

Buckets > Lyve Cloud

US - Virginia (US-East-1) Logged

https://s3.us-east-1.lyvecloud.seagate.com

Delete Bucket Delete

Step 3: Open Cyberduck – Select Bookmarks → New Bookmark

Cyberduck

File Edit View Go **Bookmark** Window Help

Open Connection

Glavis-beta s3.us-west-1.amazonaws.com GVSWK3

New Bookmark Ctrl+Shift+B

Delete Bookmark

Edit Bookmark Ctrl+E

Duplicate Bookmark


History

Bonjour


Glavis-beta

Refresh Edit Upload Transfers Disconnect Search...


Step 4: Choose Amazon S3



Step 5: Enter your Access Key



Step 6: Enter the Lyve Cloud server address using the link copied in step 2. Note the address does not contain 'https://'




- Confirm the URL has auto populated with your access key at the front of the URL address
- If the URL has not auto populated with your access key, you can manually create the address by entering

Example:


<https://YOURACCESSKEY>

@ S3 endpoint copied from step 2

<https://YOURACCESSKEY@s3.us-west-1.lyvecloud.seagate.com>





Step 7: Input your Secret Access Key




- Select to expand More Options
- In the Web URL section, add the server address obtained from step 2, this time including 'https://'
- Close the window by clicking the red 'X' box. All settings are automatically saved.

Example: <https://s3.us-west-1.lyvecloud.seagate.com>




Step 8: Connect to the Server

- Go to bookmarks or right click from within the correct, saved bookmarks.
- Select 'Connect to server'




- Your screen will show your bucket name




- Right click on your bucket name and select 'Upload'.


You may now begin uploading data to Lyve Cloud!



Optional: To confirm your connection is active, select: Bookmarks / Toggle Bookmarks



Your connection will have a green dot on the right hand side of the screen indicating an active connection.




Ready to Learn More?

Visit us at seagate.com/lyvecloud

seagate.com

© 2022 Seagate Technology LLC. All rights reserved. Seagate, Seagate Technology, and the Spiral logo are registered trademarks of Seagate Technology LLC in the United States and/or other countries. Lyve is either a trademark or registered trademark of Seagate Technology LLC or one of its affiliated companies in the United States and/or other countries. All other trademarks or registered trademarks are the property of their respective owners. Seagate reserves the right to change, without notice, product offerings or specifications. SC389.1-2208US

Documents / Resources



[**SEAGATE LYVE Cloud \[pdf\] User Guide**](#) LYVE Cloud, LYVE, Cloud

References

- [!\[\]\(e43e4b1050bbff3ab0579ed9f5c72143_img.jpg\) **The Leader in Mass Data Storage Solutions | Seagate US**](#)
- [!\[\]\(e7d3cee3a7083a6857e0f6e8a0e459d2_img.jpg\) **Lyve Cloud - Multicloud Freedom as a Service | Seagate US**](#)

[Manuals+.](#)