

Fanvil FDMS Device Management System Software Update User Guide

Home » Fanvil » Fanvil FDMS Device Management System Software Update User Guide 🖔



FDMS Update Guide

Contents

- 1 FDMS Device Management System Software Update
- 2 Documents / Resources
- **3 Related Posts**

FDMS Device Management System Software Update

Note:

- 1. The following steps are performed under the administrator account.
- 2. This document is only for customers who have installed V2.4 FDMS and need to upgrade to the latest version
- 1. Unzip the patch file provided by Fanvil, which contains the following;

名称	修改日期	类型	大小
DeviceOrientator.zip	2019/5/31 10:42	好压 ZIP 压缩文件	833 KB
FDMS_Client.zip	2019/5/31 10:42	好压 ZIP 压缩文件	13,167 KB
FDMS-Patch-XXXXXXX.zip	2019/5/31 11:54	好压 ZIP 压缩文件	39,397 KB
FdmsUpdater.zip	2019/5/31 10:42	好压 ZIP 压缩文件	147 KB
OverdueTracker.zip	2019/5/31 10:42	好压 ZIP 压缩文件	2,225 KB

2. Login FDMS and click "Stop OTS" and "Stop DOS" service;





Figure 1-2

3. In the "System Manage-> Settings", upgrade "FdmsUpdater.zip" in "Application Upgrade" module;




4. After the upgrade is completed, in the System Manage-> Settings, upgrade "FDMS-Patch-xxxxxxx.zip" in the "System Upgrade" module;


Note: Don't check System Transfer.




- 5. After the system upgrade, the system will display "login timeout" to log out of the administrator account.
- 6. Login the system administrator account again, in the System Manage—> Settings, check "Force Update" and upgrade "Fdms_Client.zip" in the "FDMS client Setting"module;



7. In the System Manage-> Settings, Upgrade two services: Overdue Data Transfer Service (OverdueTracker. Zip) and Device Orientate service (DeviceOrientator. zip) in the "Service Upgrade" module;



8. After all upgrades are completed, login to view the latest version of the current system;





Fanvil Technology Co., Ltd Ado: Level 3. Block A. Gaoxinqi 3uilding,Anhea Industrial Park, Qianjin 1 Road, 35th District, BaciAn, Shcrizhen, 519101 P.R. Tcl: 86 755 2640 2199 Fax:+86 755 2640 2518 Emali: sales@farivil.com

Documents / Resources



Fanvil FDMS Device Management System Software Update [pdf] User Guide

V2.4, FDMS Device Management System Software Update, Device Management System Soft ware Update, Management System Software Update, Software Update, Update

Manuals+,