



Home » igus » igus EduMove Mobile Robot Instruction Manual 📆



igus EduMove Mobile Robot




Contents [hide]

- 1 General Architecture
- 2 Workspace Architecture ROS
- 3 How to start for the first time
- 4 How to start mapping
- 5 How to start navigation program
- 6 Documents / Resources
 - 6.1 References

General Architecture

The control architecture of the EduMove system is modular and based on a combination of embedded computing, network communication, and the ROS2 framework:

ROS2 EduMove Package



The following key components are summarized:

Visualisierung:

• RViz2 is used to visualize robot state, sensor data, and navigation results.

Simulation:

• **Gazebo** is used as the simulation environment to model the platform and the robotic arm and to perform tests.


Navigation:

- Zur For localization and mapping, the RPLidar A2M12 is used in combination with a SLAM-Algorithmus.
- The **Nav2-Stack** is implemented for autonomous navigation, handling path planning and collision avoidance.

Workspace Architecture ROS

The packages in the ROS workspace are located in the /src folder. There are five

packages:



edumove_bringup:

- All configuration files for the workspace are stored under config, divided into software and hardware.
- All launch files are included in this package, also divided into software and hardware.
- Pre-generated maps are stored under maps.
- An automated script for map saving is located under scripts.

edumove_controllers:

• Hybrid interface for controlling the edumove platform and ReBeL-arm.

edumove_description:

• Contains meshes and URDF files for the ReBeL arm and the mobile platform.

edumove_moveit_config:

• Configuration package for using Movelt, customized for the EduMove system.

hardware_drivers:

• Repo RPLidar A2M12

How to start for the first time

The software solution can be run on a computer with ROS Jazzy installed, or in a Docker environment. Both options are also described in a README file within the ROS workspace (located in the project folder).

Hint:

- For more information for using Nav2 see Nav2 doc.
- For more information for using Movelt2 see Movelt2 doc.

With Docker, execute the following commands in a terminal started from the project folder:

```
Build the docker image for the first time, in the project folder, run this command

sudo docker compose up --build

If the image has been already built, just run:

sudo docker compose up

Whenever openning a new terminal, you should access into the docker container environment:

sudo docker exec -it ros2_jazzy_edumove_dev bash
```

Without Docker, execute the following commands in a terminal started from the project folder.

Attention: Make sure that all required packages and libraries are installed on your device (this depends on how you installed ROS). The packages can be found in the package.xml files of the ROS packages within the workspace.

For installing with rosdep (in case you not already installed rosdep)

```
install rosdep:

apt-get install python3-rosdep

install dependencies:

sudo rosdep init
  rosdep update
  rosdep install --from-paths src -y --ignore-src
```

With the dependencies installed, you can build your workspace:

```
Build the code directly in the project folder:


colcon build
```

How to start mapping

Do not forget to source the ROS workspace before launching.

```
    Launch the main program:
        ros2 launch edumove_bringup bringup.launch.py use_gui:='true' mode:='mapping'
        Prive the platform using teleop_twist_keyboard
        ros2 run teleop_twist_keyboard teleop_twist_keyboard --ros-args --remap cmd_vel:=cmd_vel/joy
        Save map:
        ros2 run edumove_bringup custom_map_saver.py --ros-args -p map_name:=edumove_map
```


A map is created as a **pgm** file, and a **yaml** file references it. The map looks as follows:




How to start navigation program

Do not forget to source the ROS workspace before launching.


The initial position must be set via the RViz interface after startup. To do this, click the following button in the top toolbar:




After that, click (and hold) on the map at the estimated position where EduMove is located, then drag in the direction EduMove is oriented, represented by the green arrow:



Setting a target position works in the same way. First, select 2D Goal Pose, then click on a point on the map and drag to set the desired target orientation. After this, the planning process within Nav2 begins:







Documents / Resources



igus EduMove Mobile Robot [pdf] Instruction Manual

EduMove Mobile Robot, EduMove, Mobile Robot, Robot

References

- User Manual
 - ► EduMove, EduMove Mobile Robot, igus, Mobile Robot,
- igus Robot

Leave a comment

Your email address will not be published. Required fields are marked*

Comment*

Name

Email

Website

☐ Save my name, email, and website in this browser for the next time I comment.

Post Comment

Search:

e.g. whirlpool wrf535swhz

Search

Manuals+ | Upload | Deep Search | Privacy Policy | @manuals.plus | YouTube

This website is an independent publication and is neither affiliated with nor endorsed by any of the trademark owners. The "Bluetooth®" word mark and logos are registered trademarks owned by Bluetooth SIG, Inc. The "Wi-Fi®" word mark and logos are registered trademarks owned by the Wi-Fi Alliance. Any use of these marks on this website does not imply any affiliation with or endorsement.