

RELEASE NOTES: LXSoftware v 11.10.6

Released: July 30, 2025

Minor Updates

- Refinements to LX7 support
- Updated functionality check document

RELEASE NOTES: LXSoftware v 11.10.5

Released: June 6, 2025

Major Updates

- Add support for LX7

Minor Updates

- Change to false the default value for setting that determines whether to require user to login

RELEASE NOTES: LXSoftware v 11.10.4

Released: December 3, 2024

Minor Updates

- Remove message related to Polyscore that appeared when setting question timer to less than 25 seconds
- Remove “Record” button for Audio Clip in Question Editor; this function is no longer supported



RELEASE NOTES: LXSoftware v 11.10.x

Bug Fixes

- Resolve significant issues related to Masseter Headset
 - The Masseter trace and settings tab would generally not appear, even though Masseter was connected and enabled in Administrator preferences
 - Devices -> Restart All would sometimes cause software crash when Masseter connected

RELEASE NOTES: LXSoftware v 11.10.3

Released: October 29, 2024

Minor Updates

- Remove PolyScore
- Modify RLE constraints to natural log of 1.2 – 1.6 in both positive and negative directions
- Replace the obsolete Functionality Check hardware manual with document describing how to perform a Field Functionality Check

Bug Fixes

- Resolve issue that when scoresheet was configured to show only one pneumo sensor the pneumo score was not added to the subtotal

RELEASE NOTES: LXSoftware v 11.10.2

Released: August 21, 2024

Bug Fixes

- Resolve issue with NCCA import that Automatic EDA data would be incorrectly imported as Manual EDA data

RELEASE NOTES: LXSoftware v 11.10.1

Released: August 15, 2024

Minor Updates

- If not already present, automatically install Microsoft Visual C++ 2015-2022 Redistributable Package
- For NCCA export, stop adding “R” or “C”, if missing, to Relevant or Comparison question labels, respectively
- Added the Import and Export buttons back to the Question Manager

Bug Fixes

- Resolve issue that “Documents and Attachments” menu item did not bring up the expected window
- Resolve issue that duplicate PFs (ending in ~1, ~2, etc.) were being created when opening PF using file explorer or folder browser

RELEASE NOTES: LXSoftware v 11.10.0

Released: August 6, 2024

Major Updates

- Update Build tools to MVC142
- Update to C++17
- Downgrade Video Capture library to version used in 11.8.6.399; this resolves significant issues that were seen during video and audio recording
- Prevent installing over existing LXSoftware install
 - If user attempts to install over existing LXSoftware, displays message box with instructions

Minor Updates

- ESS
 - Correctly compute the number of control questions on old PFs
 - Ensure that Prior Odds appear in the ESS report and in the PDF
- Masseter Headset
 - Emplace UI to allow selection of the headset under Preferences->Admin
- Allow for registry configuration to prevent usage of FTP or scripting
- Remove support for the Dari language
- Change default Activity Seat gain from 5.0 to 1.0

RELEASE NOTES: LXSoftware v 11.10.x

- Stop resizing Recorder application when selecting a different camera
- Add the OSS-3 manual to the Polygraph References library
- Remove “Transfer Files via FTP” from the Tools menu
- Removed the Import and Export buttons from the Question Manager

Bug Fixes

- ESS
 - Resolve chart selection error
 - Fix issue that extra text would sometimes appear in the ESS Report title
- Masseter Headset
 - Resolve class of merge errors due to timing differences
- Fix setting that turns off warning that appears when creating new series
- Fix minor issues with text appearance when adjusting gain
- Resolve issue that could cause LXSoftware to freeze
- Fix the scoring artifact character in Spanish and Russian versions