
June 21, 2022

### Contents

General	. 1
Copyright Notice	. 1
End User License Agreement	. 1
Revision History	. 1
Installation Instructions	. 4
Finding the Current Software Version	. 4

### General



This software is ONLY compatible with these model wall controls.:

SYSTXCCITC01-C

The series C software is available by Over The Air (OTA) only.

**Note:** This software is for the Series C controls only. The Series A or B controls cannot use Series C software and vice-versa.

### **Copyright Notice**

Carrier Corporation is the copyright owner of this material. Copyright laws and international copyright treaties, as well as other intellectual property laws and treaties protect this software update package. User may not and shall not copy or otherwise reproduce or make available to any other party any part of or the entire software update package.

#### **End User License Agreement**

The user MUST read and accept the **End User License Agreement** included with this software package BEFORE downloading and installing this software on the wall control.

## **Revision History**

### **Version 1.11 (June 2022)**

Version 1.11 software includes the following updates to the Series C Carrier® Infinity® System Control:

- System monitor implemented to prevent over conditioning including a high and low temperature alert
- WPA3 security compatibility for Wi-Fi connection
- Functionality added for selection of new evaporator V Coil in the discovery screens
- New Over The Air (OTA) Status Indicator on the idle screen to indicate new firmware is being downloaded
- Temperature compensation algorithm improved for better temperature accuracy

June 21, 2022

- Time synchronization corrected so it synchronizes immediately when enabled
- Equipment summary updated to reflect correct outdoor unit size with NIM application.
- SAM Module compatibility added
- Wi-Fi advanced options are now available
- "All zones hold" no longer results in a quick timeout on the main screen

June 21, 2022

Version 1.05 PRODUCTION (February 2, 2022)

Initial release

June 21, 2022

### **Installation Instructions**

### Finding the Current Software Version

The software installation process is Over The Air (OTA) only. The current software version may be determined as follows:

Press menu on the Main screen,



and then the down-arrow to go to the second menu screen.




Touch service icon.



June 21, 2022

Touch model/serial numbers on the resulting screen.



Touch wall control on the resulting screen.



View the Software Version number.

Software Version 131755-01.11, for example, is the production software version 1.11, released in July 2022.

