

PeakTech 5185 Data Logger User Guide

Home » PeakTech » PeakTech 5185 Data Logger User Guide 🖺

Contents

- 1 PeakTech 5185 Data Logger
- **2 Product Information**
- **3 Product Usage Instructions**
- 4 Software installation
- **5 Documents / Resources**
 - **5.1 References**



PeakTech 5185 Data Logger



Product Information

Specifications

• Product Name: Data Logger

• Model Number: [Insert Model Number]

• Version: [Insert Version Number]

Product Usage Instructions

Software Installation

To install the software, please follow the steps below:

- 1. Download the current software from the following link: Software Download Link
- 2. Extract the downloaded file to a location on your computer.
- 3. Locate the Software EN folder within the extracted files.
- 4. Double-click on the Setup.exe file in the Software EN folder.
- 5. Follow the on-screen instructions to complete the installation.

Data Logger Setup

To put the data logger into operation, please follow the steps below:

- 1. Plug in the data logger to your computer using the provided USB cable.
- 2. Open the Software EN folder on your computer.
- 3. Navigate to the "program files" subfolder within the Software EN folder.
- 4. Locate and open the "data logger" subfolder.
- 5. Select the "Data Logger Graph.exe" file.

The data logger software will now open and you can start using the device.


Frequently Asked Questions (FAQ)

- Q: Do I need to install any drivers for the data logger?
 - A: For the new version from SN 230324, no driver installation is necessary as the data logger is recognized as an external drive and automatically installed with system drivers.
- Q: Can I evaluate data without using the software?
 - A: No, data can only be evaluated using the software. The device must be used in connection with the software.
- Q: What languages are available in the software?
 - A: The software provides language support for English (EN) and French (FR). Only copy the language folder that you require.

NOTE: With the new version from SN 230324, no driver installation is necessary because the data logger is recognized as an external drive and is automatically installed with system drivers. However, data can only be evaluated via the software.


Software installation

- Firstly download the current SW https://www.peaktech.de/media/d2/16/a4/1684836681/PeakTech_5185-5187 Software%20ab%20SN%20230324.zip
- To put the data logger into operation, you must first copy the content of the enclosed CD to your PC. The Software EN folder corresponds to the English version. Languages that are not required do not need to be copied
- Double-click the "Setup.exe" file in the Software EN folder and follow the setup instructions



Plug in the data logger and open the folder Software EN >program files > subfolder data logger. Select the

"Data Logger Graph.exe" file there. The data logger software will now open.



Notice:

The device can only be used in connection with the software.

Documents / Resources



References

User Manual

Manuals+, Privacy Policy