



Software s Datacolor Sort Software Installation Guide

[Home](#) » [Software s](#) » Software s Datacolor Sort Software Installation Guide 



Contents

- [1 Datacolor Sort Software](#)
- [2 Installation Overview](#)
- [3 Installation Procedure](#)
- [4 Validating Datacolor Software](#)
- [5 Documents / Resources](#)
- [6 Related Posts](#)

Datacolor Sort Software

Datacolor MATCH^{SORT}™ Stand-Alone Installation Guide (July, 2021)

All efforts have been made to ensure the accuracy of the information presented in this format. However, should any errors be detected, Datacolor appreciates your efforts to notify us of these oversights.

Changes are periodically made to this information and are incorporated into forthcoming versions. Datacolor reserves the right to make improvements and/or changes in the product(s) and/or program(s) described in this material at any time.

© 2008 Datacolor. Datacolor, SPECTRUM and other Datacolor product trademarks are the property of Datacolor. Microsoft and Windows are either registered trademarks of Microsoft Corporation in the United States and/or other countries.

To obtain information on local agents, contact either of the offices listed below, or visit our website at www.datacolor.com.

Support Questions?

If you need help with a Datacolor product, please contact one of our top-rated technical support teams located around the world for your convenience. You can find contact information below for the Datacolor office in your

area.

Americas

+1.609.895.7465

+1.800.982.6496 (toll-free)

+1.609.895.7404 (fax)

NSASupport@datacolor.com

Europe

+41.44.835.3740

+41.44.835.3749 (fax)

EMASupport@datacolor.com

Asia Pacific

+852.2420.8606

+852.2420.8320 (fax)

ASPSupport@datacolor.com

Or Contact Your Local Representative

Datacolor has representatives in over 60 countries.

For a complete list, visit www.datacolor.com/locations.

Manufactured by Datacolor

5 Princess Road

Lawrenceville, NJ 08648

1.609.924.2189

Committed to Excellence. Dedicated to Quality. Certified to ISO 9001 in Manufacturing Centers Worldwide.

Installation Overview

This document describes the installation of Datacolor Software to your computer's hard disk. If you have purchased your computer from us, the software will be already installed. If you purchased your own computer, follow these instructions to install our software on your computer.

Before you begin the installation, you should have all installation USB's, and Microsoft Windows* should be properly installed on your computer.

1.1 System Requirements

The system requirements shown below are the minimum configuration to ensure effective operation of the standard Datacolor SORT software. Configurations below stated requirements may work but are not supported by Datacolor.

Component	Recommended	
Processor	Dual Core processor	1
Memory RAM	8 GB	1
Free Hard Drive Capacity	500 GB	1
Video Resolution	True Color	2
Available Ports	(1) RS-232 Serial (for older spectrophotometers) (3) USB	3
Operating System	Windows 10 (32 or 64 bit)	4
Email (for supported level)	Outlook 2007 or above, POP3	
Authenticated Sybase Database supplied with the system	Sybase 12.0.1. EBF 3994	
Optional Textile Database for SQL upon request	Microsoft SQL Server 2012	5
Server OS	Microsoft Server 2016	6

Notes:

1. Minimum system configurations may limit performance, data capacity and operation of some features. Faster processor, more memory and faster hard drives will significantly enhance performance.
2. Accurate on-screen color display requires monitor calibration and true-color video mode.
3. Datacolor spectrophotometers use either an RS-232 Serial or USB connectors. Datacolor Spyder5™ requires a universal serial bus (USB) connection. Printer port requirements (Parallel or USB...) depend on the specific printer selected.
4. Windows 32 bit and 64 bit operating systems are supported. 64 bit hardware running Windows 32 bit operating system is supported. Datacolor Tools is a 32 bit application. 64 bit hardware running Windows 32 bit operating system is supported.
5. Microsoft SQL Server 2012 is supported on Tools textile database..
6. Windows Server 2016 is supported.

Before You Begin

- Microsoft Windows® should be properly installed on your computer.
- You must have Windows Administrator rights to install this software.
- Restart the system before installing the software. This removes any memory-resident modules that may interfere with the installation and is especially important if you have been running a previous version.
- Install Sybase V12 database management software.
- Close all other programs that are running.
- Have all program installation readily available.

Important, Before You Begin! You must have Administrator Rights to install this software and you must have installed Sybase first!

Installation Procedure

To install Datacolor SORT

1. Place the Datacolor SORT USB into the port.
2. Select the Menu.exe

The Main Installation menu should appear automatically:




Select Install Datacolor SORT



When the Main Installation Menu is displayed, choose "Install Datacolor Sort" The installation will guide you through installation.

Select a language from the list box.(Language include Chinese (simplified), Chinese (traditional), English, French


(standard), German, Italian, Japanese, Portuguese (standard) and Spanish.)



Click "Next". The installation wizard will start – follow the prompts to install Datacolor SORT on your computer. The next dialogs only appear if pre Spectrum software is already installed on the system. If it's a new installation the Setup proceeds with the Welcome dialog.

When you upgrade from SmartSort1.x to Datacolor Datacolor SORT v1.5, the Setup uninstalls the old software before the new Software is installed (DCIMatch; SmartSort; .CenterSiceQC, Fibramix, matchExpress or Matchpoint)

The Setup asks if you have made a backup of your entire database. If not, clock 'No' to exit the setup.





Depending on the installed software you are informed about the un-installation process. The Setup program shows a message for each program that should be installed.



- Uninstalling DCIMatch






- Uninstalling CenterSideQC (if installed)



- Uninstalling Fibratrix (if installed)




- Uninstalling SmartSort (if installed)




If you are installing Datacolor SORT for the first time, click "Next" to access the Datacolor Software License Agreement dialog. You must select the acceptance radio button in order to install Datacolor SORT. If you are upgrading an existing, licensed copy of Datacolor Match, this screen will not appear.



Select the acceptance radio button and click the "Next" button to proceed.





Local Area Network (LAN)


Click "Next" to select default installation folder. Normal default is C:\Program Files\Datacolor

Setup types

You will now see a screen offering you several different setup options.

Complete

(All modules are installed on your computer.)




Select the Setup Type to install and click "Next".

Custom:


Please note, this is not recommended for typical user installations.

Custom setup allows you to install specific features instead of the entire Datacolor SORT installation.




Click " Next " to select the shortcuts to install .


At default, the installation will put Datacolor SORT icon on your desktop and a shortcut to start program menu.




Click " Next " to continue the installation.



Click "Install" to transfer the data
Setup starts transferring the files





The 'DataSecurityClient' is installed

The Datacolor security software is installed now:




followed by installing the Datacolor Envision components:




followed by installing the instrument drivers:






Followed by installing the Acrobat Reader



Click "Yes" to start the Acrobat reader installation and follow the instructions.
Finally, the "Complete" screen display.
Click "Yes" to start the Acrobat reader installation and follow the instructions.
Finally, the "Complete" screen display.



Click “ Finish ” to restart your computer.
Datacolor SORT is now installed on your system!

Validating Datacolor Software

Datacolor Spectrum Software is protected from unauthorized use by a software license. When the software is initially installed, the software license is in a demo period that will allow access for a fixed amount of time. In order to run the software after the demo period, the software license must be validated.

There are a number of ways to validate the software. In general you will need the following information:

1. You will need the Serial Number for your software. This number is supplied by Datacolor and is found on the USB case.
2. You will need a Computer Validation Number. This number is generated by the security software and is unique to your computer.

Validation information is accessed and input in the Datacolor Validation Window shown below:

datacolor Security Client Ver 4

The Unlock Response Number will update this product with new features.

300: 1 of 10 Licenses used

[Internet enabled users may validate now by clicking on this link.](#)

Otherwise, to validate your software, please visit <http://pmweb.datacolor.com>. If you do not have access to the internet, you can email the requested information from the enclosed form to SoftwareLicense@Datacolor.com or phone your local sales office or dial 1-800-982-6496 for toll free service in the U.S. and Canada.

Serial Number

1280928015

Computer Validation Number

A309281740279-7167774

Unlock Response Number

It may take up to seven days to validate your software. Please do so as soon as possible so that you won't be without the use of this software.

Continue

Version 4.2.0

Datacolor Tools will display the Validation Window every time it starts during the demo period. The Validation Window can be accessed from "About" window in Datacolor Tools, select "License Info".

You can validate the software in 3 ways:

- Using a Web Connection – Link is on the Validation Window. Example is shown below
- E-Mail – Send Serial Number and Computer Validation Number for the product to SoftwareLicense@Datacolor.Com. You will receive an Unlock Response Number by e-mail that you will put into the Validation Window.
- Phone – In the US and Canada phone toll free **1-800-982-6496** or call you local sales office. Youwill need the Serial Number and the Computer Validation Number for the product. You will be given an Unlock Response Number that you will put into the Validation Window.

datacolor Security Client Ver 4

The Unlock Response Number will update this product with new features.

300: 1 of 10 Licenses used

[Internet enabled users may validate now by clicking on this link.](#)
Otherwise, to validate your software, please visit <http://pmweb.datacolor.com>. If you do not have access to the internet, you can email the requested information from the enclosed form to SoftwareLicense@Datacolor.com or phone your local sales office or dial 1-800-982-6496 for toll free service in the U.S. and Canada.

Serial Number
1280928015

Computer Validation Number
A309281740279-7167774

Unlock Response Number

It may take up to seven days to validate your software. Please do so as soon as possible so that you won't be without the use of this software.

Continue

Version 4.2.0

Type the Serial Number for the product into this field.

Tip: To avoid retyping this number later, highlight the number and then copy it to the clipboard using the Ctrl-C command.

Click the link to go to the Datacolor Software Validation Web Service.

Welcome to Datacolor's software validation web service. To validate your software, please enter the following information, then press continue.

First Name: John

Last Name: Doe

E-Mail: xyz@company.com

Serial Number: 1217185437

Continue

[Contact Webmaster](#)

Type a contact name in the First Name and Last Name fields.

Give your e-mail address.

Input the product Serial Number.

Tip: Paste it if you copied it earlier.

Click the Continue button.

The serial number you entered is for Datacolor Match Pigment Datacolor Match Pigment Plus.
Your Order Number is 123456.

Please verify that this purchase information is correct. If you have questions, click "Contact Webmaster".

Press Continue to validate your software.

[Continue](#) [Back](#) [Contact Webmaster](#)

This screen verifies that the serial number is valid and displays information about the product.

Click the Continue button to proceed.

ODBC Data Source Administrator

Please enter your Computer Validation Number as displayed in your Datacolor Software:

[Validate](#)

After entering the Computer Validation Number, click Validate to continue.

Enter the Computer Validation Number from the Validation Window.

Tip: You can copy this number on the clipboard from the Validation Window and paste it in here.

[Validate Another](#) [Close This Window](#) [Contact Webmaster](#)

Please enter your Computer Validation Number as displayed in your Datacolor Software:

[Validate](#)

Unlock Response Number:

Please enter the above Unlock Response Number into the Unlock Response Number section of your Datacolor Software validation screen.

An email has been sent to bbinder@datacolor.com with confirmation of this transaction. Please keep this for your records.

[Validate Another](#) [Close This Window](#) [Contact Webmaster](#)

This is your Unlock Response Number. Enter this number into the Validation Screen on your computer.

Tip: You can copy this number on the clipboard and paste it into the Validation Screen.

After you have entered the Unlock Response Number into the Validation Screen, your software is validated. You can validate additional programs by selecting the Validate Another option ODBC Data Source Administrator

SOFTWARE

tagline is here

Documents / Resources

 <p>Datacolor SORT Installation Guide</p>	<p>Software s Datacolor Sort Software [pdf] Installation Guide</p> <p>Datacolor Sort Software</p>
----------------------------------------------------------------------------------------------------------------------------------	-------------------------------------------------------------------------------------------------------------------