Home » Support » How to log in CP900's setting interface?

# How to log in CP900's setting interface?

#### **Contents**

- 1 How to log in CP900's setting interface?
- 2 Application introduction:
- **3 DOWNLOAD**
- **4 Related Posts**

# How to log in CP900's setting interface?

It is suitable for: CP900\_V1

# **Application introduction:**


If you want to login to CP900's setting interface to configure some settings, please follow the steps below.

#### STEP-1: Client mode


- 1-1. Connect your computer to the router by cable or wireless
- 1-2. Setup you PC to get the IP automatically (Here I take system W10 for example)
- 1-3. Click on at the bottom right corner on the screen



1-4. Click [Properties] button in the lower left corner



1-5. Double click on "Internet Protocol (TCP/IP)".




STEP-2:


Now you have two ways to configure the TCP/IP protocol below

#### 2-1. Use the first default IP address 192.168.0.254:

Assigned manually IP address 192.168.0.x "x" range from 2 to 253, the Subnet Mask is 255.255.255.0 and Gateway is 192.168.0.254.



Enter 192.168.0.254 into the address bar of your browser. Log in the settings interface.




### [Note]:


192.168.0.254 can only be used in AP mode and WISP mode; Client mode and Repeater mode please use his second IP address 169.254.0.254.

#### 2-2. Use the second IP address 169.254.0.254:

Assigned manually IP address 169.254.0.x "x" range from 2 to 253, the Subnet Mask is 255.255.255.0 and Gateway is 169.254.0.254.



Enter 169.254.0.254 into the address bar of your browser. Log in the settings interface.




# [Note]:

169.254.0.254 supports login in Client mode, Repeater mode, AP mode and WISP mode.

#### STEP-3:

After the setup is successful, your computer must choose to obtain an IP address automatically to access the network. As the picture shows.



# **DOWNLOAD**

How to log in CP900's setting interface – [Download PDF]

Manuals+,