



Wasp Portal Knowledgebase Software Labeler Instructions

[Home](#) » [Wasp](#) » Wasp Portal Knowledgebase Software Labeler Instructions 



Contents

- [1 Knowledgebase Software Labeler](#)
- [2 Documents / Resources](#)
 - [2.1 References](#)
- [3 Related Posts](#)

Knowledgebase Software Labeler

Portal > Knowledgebase > Software > Labeler > Labeler – Installation – Labeler installed as Admin says it is in Demo mode when run as the user.

Labeler – Installation – Labeler installed as Admin says it is in Demo mode when run as the user.

Internal User – 2017-04-10 – in Labeler

The user needs to be given read/write access for the directory C:\Program Files\Wasp Technologies, and full control to the registry key HKEY_LOCAL_MACHINE\SOFTWARE\Wasp Technologies. After that, it should allow the user to open the program correctly.

Documents / Resources



[Wasp Portal Knowledgebase Software Labeler](#) [pdf] Instructions

Portal Knowledgebase Software Labeler, Knowledgebase Software Labeler, Software Labeler, Labeler

References

- [Wasp Helpdesk](#)
- [Knowledgebase - Wasp Helpdesk](#)
- [Labeler - Installation - Labeler installed as Admin says it is in Demo mode when run as the user. - Knowledgebase / Software / Labeler - Wasp Helpdesk](#)
- [Knowledgebase / Software / Labeler - Wasp Helpdesk](#)
- [Knowledgebase / Software - Wasp Helpdesk](#)
- [User Manual](#)